

# NAG Library Routine Document

## F11GTF

**Note:** before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

### 1 Purpose

F11GTF is the third in a suite of three routines for the iterative solution of a complex Hermitian system of simultaneous linear equations (see Golub and Van Loan (1996)). F11GTF returns information about the computations during an iteration and/or after this has been completed. The first routine of the suite, F11GRF, is a setup routine, the second routine, F11GSF is the proper iterative solver.

These three routines are suitable for the solution of large sparse complex Hermitian systems of equations.

### 2 Specification

```

SUBROUTINE F11GTF(ITN, STPLHS, STPRHS, ANORM, SIGMAX, ITS, SIGERR, WORK,
1                LWORK, IFAIL)
    INTEGER      ITN, ITS, LWORK, IFAIL
    double precision STPLHS, STPRHS, ANORM, SIGMAX, SIGERR
    complex*16      WORK(LWORK)

```

### 3 Description

F11GTF returns information about the solution process. It can be called either during a monitoring step of F11GSF or after F11GSF has completed its tasks. Calling F11GTF at any other time will result in an error condition being raised.

For further information you should read the documentation for F11GRF and F11GSF.

### 4 References

Golub G H and Van Loan C F (1996) *Matrix Computations* (3rd Edition) Johns Hopkins University Press, Baltimore

### 5 Parameters

- |    |  |               |
|----|--|---------------|
| 1: | ITN – INTEGER  | <i>Output</i> |
|    | <i>On exit:</i> the number of iterations carried out by F11GSF.  |               |
| 2: | STPLHS – <i>double precision</i>   | <i>Output</i> |
|    | <i>On exit:</i> the current value of the left-hand side of the termination criterion used by F11GSF.   |               |
| 3: | STPRHS – <i>double precision</i>   | <i>Output</i> |
|    | <i>On exit:</i> the current value of the right-hand side of the termination criterion used by F11GSF.  |               |
| 4: | ANORM – <i>double precision</i>  | <i>Output</i> |
|    | <i>On exit:</i> the norm $\ A\ _1 = \ A\ _\infty$ when either it has been supplied to F11GRF or it has been estimated by F11GSF (see also Sections 3 and 5 in F11GRF). Otherwise, ANORM = 0.0 is returned. |               |

5: SIGMAX – *double precision* *Output*

*On exit:* the current estimate of the largest singular value  $\sigma_1(\bar{A})$  of the preconditioned iteration matrix  $\bar{A} = E^{-1}AE^{-T}$ , when either it has been supplied to F11GRF or it has been estimated by F11GSF (see also Sections 3 and 5 in F11GRF). Note that if  $ITS < ITN$  then SIGMAX contains the final estimate. If, on final exit from F11GSF,  $ITS = ITN$ , then the estimation of  $\sigma_1(\bar{A})$  may have not converged: in this case you should look at the value returned in SIGERR. Otherwise, SIGMAX = 0.0 is returned.

6: ITS – INTEGER *Output*

*On exit:* the number of iterations employed so far in the computation of the estimate of  $\sigma_1(\bar{A})$ , the largest singular value of the preconditioned matrix  $\bar{A} = E^{-1}AE^{-T}$ , when  $\sigma_1(\bar{A})$  has been estimated by F11GSF using the bisection method (see also Sections 3, 5 and 8 in F11GRF). Otherwise, ITS = 0 is returned.

7: SIGERR – *double precision* *Output*

*On exit:* if  $\sigma_1(\bar{A})$  has been estimated by F11GSF using bisection,

$$\text{SIGERR} = \max \left( \frac{|\sigma_1^{(k)} - \sigma_1^{(k-1)}|}{\sigma_1^{(k)}}, \frac{|\sigma_1^{(k)} - \sigma_1^{(k-2)}|}{\sigma_1^{(k)}} \right),$$

where  $k = ITS$  denotes the iteration number. The estimation has converged if SIGERR  $\leq$  SIGTOL where SIGTOL is an input parameter to F11GRF. Otherwise, SIGERR = 0.0 is returned.

8: WORK(LWORK) – *complex\*16* array *Communication Array*

*On entry:* the workspace WORK as returned by F11GSF (see also Section 3 in F11GSF).

9: LWORK – INTEGER *Input*

*On entry:* the dimension of the array WORK as declared in the (sub)program from which F11GTF is called (see also Section 5 in F11GRF).

*Constraint:* LWORK  $\geq$  120.

**Note:** although the minimum value of LWORK ensures the correct functioning of F11GTF, a larger value is required by the iterative solver F11GSF (see also Section 5 in F11GRF).

10: IFAIL – INTEGER *Input/Output*

*On entry:* IFAIL must be set to 0, -1 or 1. If you are unfamiliar with this parameter you should refer to Section 3.3 in the Essential Introduction for details.

*On exit:* IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, if you are not familiar with this parameter, the recommended value is 0. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**

## 6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = -*i*

On entry, the *i*th argument had an illegal value.

IFAIL = 1

F11GTF has been called out of sequence. For example, the last call to F11GSF did not return IREVCM = 3 or 4.

## **7 Accuracy**

Not applicable.

## **8 Further Comments**

None.

## **9 Example**

See Section 9 in F11GRF.

---