# **NAG Library Routine Document**

# **G05RKF**

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

# 1 Purpose

G05RKF generates pseudorandom uniform variates with joint distribution of a Gumbel-Hougaard Archimedean copula.

# 2 Specification

```
SUBROUTINE GO5RKF (N, M, THETA, SORDER, STATE, X, LDX, SDX, IFAIL)

INTEGER N, M, SORDER, STATE(*), LDX, SDX, IFAIL

REAL (KIND=nag_wp) THETA, X(LDX,SDX)
```

# 3 Description

Generates n pseudorandom uniform m-variates whose joint distribution is the Gumbel-Hougaard Archimedean copula  $C_{\theta}$ , given by

$$C_{\theta} = \exp \left\{ -\left[ \left( -\ln u_{1} \right)^{\theta} + \left( -\ln u_{2} \right)^{\theta} + \dots + \left( -\ln u_{m} \right)^{\theta} \right] \right\}, \quad \begin{cases} \theta \in (1, \infty), \\ u_{j} \in (0, 1], \quad j = 1, 2, \dots m; \end{cases}$$

with the special cases:

 $C_1 = u_1 u_2 \cdots u_m$ , the product copula;

 $C_{\infty} = \min(u_1, u_2, \dots, u_m)$ , the Fréchet-Hoeffding upper bound.

The generation method uses mixture of powers.

One of the initialization routines G05KFF (for a repeatable sequence if computed sequentially) or G05KGF (for a non-repeatable sequence) must be called prior to the first call to G05RKF.

### 4 References

Marshall A W and Olkin I (1988) Families of multivariate distributions *Journal of the American Statistical Association* **83** 403

Nelsen R B (2006) An Introduction to Copulas (2nd Edition) Springer Series in Statistics

#### 5 Parameters

1: N – INTEGER Input

On entry: n, the number of pseudorandom uniform variates to generate.

Constraint:  $N \ge 0$ .

2: M – INTEGER Input

On entry: m, the number of dimensions.

Constraint:  $M \ge 2$ .

Mark 25 G05RKF.1

G05RKF NAG Library Manual

3: THETA - REAL (KIND=nag wp)

Input

On entry:  $\theta$ , the copula parameter.

*Constraint*: THETA  $\geq 1.0$ .

#### 4: SORDER – INTEGER

Input

On entry: determines the storage order of variates; the (i,j)th variate is stored in X(i,j) if SORDER = 1, and X(j,i) if SORDER = 2, for i = 1, 2, ..., n and j = 1, 2, ..., m.

Constraint: SORDER = 1 or 2.

### 5: STATE(\*) – INTEGER array

Communication Array

**Note**: the actual argument supplied **must** be the array STATE supplied to the initialization routines G05KFF or G05KGF.

On entry: contains information on the selected base generator and its current state.

On exit: contains updated information on the state of the generator.

6: X(LDX, SDX) - REAL (KIND=nag wp) array

Output

On exit: the pseudorandom uniform variates with joint distribution described by  $C_{\theta}$ , with X(i, j) holding the *i*th value for the *j*th dimension if SORDER = 1 and the *j*th value for the *i*th dimension of SORDER = 2.

7: LDX – INTEGER

Input

On entry: the first dimension of the array X as declared in the (sub)program from which G05RKF is called.

Constraints:

```
if SORDER = 1, LDX \geq N; if SORDER = 2, LDX \geq M.
```

8: SDX – INTEGER

Input

On entry: the second dimension of the array X as declared in the (sub)program from which G05RKF is called.

Constraints:

```
if SORDER = 1, SDX \ge M; if SORDER = 2, SDX \ge N.
```

#### 9: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. If you are unfamiliar with this parameter you should refer to Section 3.3 in the Essential Introduction for details.

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, if you are not familiar with this parameter, the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

On exit: IFAIL = 0 unless the routine detects an error or a warning has been flagged (see Section 6).

G05RKF.2 Mark 25

# 6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, corrupt STATE parameter.

IFAIL = 2

On entry, invalid THETA: THETA =  $\langle value \rangle$ . Constraint: THETA  $\geq 1.0$ .

IFAIL = 3

On entry,  $N = \langle value \rangle$ . Constraint:  $N \ge 0$ .

IFAIL = 4

On entry,  $M = \langle value \rangle$ . Constraint:  $M \ge 2$ .

IFAIL = 5

On entry, invalid SORDER. Constraint: SORDER = 1 or 2.

IFAIL = 7

On entry, LDX must be at least  $\langle value \rangle$ : LDX =  $\langle value \rangle$ .

IFAIL = 8

On entry, SDX must be at least  $\langle value \rangle$ : SDX =  $\langle value \rangle$ .

IFAIL = -99

An unexpected error has been triggered by this routine. Please contact NAG.

See Section 3.8 in the Essential Introduction for further information.

IFAIL = -399

Your licence key may have expired or may not have been installed correctly.

See Section 3.7 in the Essential Introduction for further information.

IFAIL = -999

Dynamic memory allocation failed.

See Section 3.6 in the Essential Introduction for further information.

# 7 Accuracy

Not applicable.

### 8 Parallelism and Performance

G05RKF is threaded by NAG for parallel execution in multithreaded implementations of the NAG Library.

Mark 25 G05RKF.3

G05RKF NAG Library Manual

Please consult the X06 Chapter Introduction for information on how to control and interrogate the OpenMP environment used within this routine. Please also consult the Users' Note for your implementation for any additional implementation-specific information.

### **9** Further Comments

In practice, the need for numerical stability restricts the range of  $\theta$  such that:

if  $(\theta - 1) < 1.0 \times 10^{-6}$ , the routine returns pseudorandom uniform variates with  $C_1$  joint distribution;

if  $\theta > \max(80.0, -0.5 \ln \epsilon_s)$ , the routine returns pseudorandom uniform variates with  $C_{\infty}$  joint distribution;

where  $\epsilon_s$  is the safe-range parameter, the value of which is returned by X02AMF.

# 10 Example

This example generates thirteen four-dimensional variates for copula  $C_{2,4}$ .

### 10.1 Program Text

```
Program g05rkfe
     GO5RKF Example Program Text
     Mark 25 Release. NAG Copyright 2014.
      .. Use Statements ..
     Use nag_library, Only: g05kff, g05rkf, nag_wp, x04caf
      .. Implicit None Statement ..
!
     Implicit None
     .. Parameters ..
                                       :: lseed = 1, nin = 5, nout = 6
     Integer, Parameter
     .. Local Scalars ..
     Real (Kind=nag_wp)
                                       :: theta
                                       :: genid, ifail, ldx, lstate, m, n,
     Integer
                                          sdx, sorder, subid
      .. Local Arrays ..
     Real (Kind=nag_wp), Allocatable :: x(:,:)
     Integer
                                      :: seed(lseed)
     Integer, Allocatable
                                       :: state(:)
!
      .. Executable Statements ..
     Write (nout,*) 'GO5RKF Example Program Results'
     Write (nout,*)
     Flush (nout)
     Skip heading in data file
1
     Read (nin,*)
     Read in the base generator information and seed
     Read (nin,*) genid, subid, seed(1)
     Initial call to initialiser to get size of STATE array
!
      lstate = 0
     Allocate (state(lstate))
     ifail = 0
     Call g05kff(genid, subid, seed, lseed, state, lstate, ifail)
     Reallocate STATE
     Deallocate (state)
     Allocate (state(lstate))
     Initialize the generator to a repeatable sequence
      ifail = 0
     Call g05kff(genid, subid, seed, lseed, state, lstate, ifail)
```

G05RKF.4 Mark 25

```
Read in sample size, number of dimensions and order
     Read (nin,*) n, m, sorder
     If (sorder==1) Then
1
       X(N,M)
        ldx = n
        sdx = m
     Else
!
        X(M,N)
        ldx = m
       sdx = n
     End If
     Allocate (x(ldx,sdx))
     Read in parameter
     Read (nin,*) theta
     Generate variates
     ifail = 0
     Call g05rkf(n,m,theta,sorder,state,x,ldx,sdx,ifail)
     Display the variates
     If (sorder==1) Then
!
       X(N,M)
        ifail = 0
        Call x04caf('General',' ',n,m,x,ldx, &
          'Uniform variates with copula joint distribution', ifail)
     Else
!
        X(M,N)
        ifail = 0
        Call x04caf('General',' ',m,n,x,ldx, &
          'Uniform variates with copula joint distribution', ifail)
    End Program g05rkfe
```

# 10.2 Program Data

```
GO5RKF Example Program Data

1 1 1762543 :: GENID, SUBID, SEED(1)

13 4 1 :: N,M, SORDER

2.4 :: THETA
```

#### 10.3 Program Results

GO5RKF Example Program Results

```
Uniform variates with copula joint distribution
          1
                 2
                          3
    0.9369 0.8676 0.9713 0.8854
0.1139 0.3063 0.8625 0.2743
2
    0.4418 0.2211 0.5042 0.4985
3
   0.7902 0.6007 0.7493 0.6474
    0.8362 0.9847 0.8807
0.1781 0.4610 0.1283
5
                             0.9079
6
                             0.1329
    0.1272 0.1760 0.1805
7
                             0.0383
8
    0.4473 0.2171 0.1662
                             0.1300
                             0.8879
9
    0.8899 0.9005 0.8844
10
    0.9069
            0.8681
                     0.8450
                             0.8804
    0.2222 0.5499 0.4965
11
                             0.6488
    0.3807 0.5967 0.5096 0.3577
12
   0.8445 0.7755 0.8661 0.8948
13
```

Mark 25 G05RKF.5 (last)