

NAG Toolbox

nag_lapack_ztrsna (f08qy)

1 Purpose

nag_lapack_ztrsna (f08qy) estimates condition numbers for specified eigenvalues and/or right eigenvectors of a complex upper triangular matrix.

2 Syntax

```
[s, sep, m, info] = nag_lapack_ztrsna(job, howmny, select, t, vl, vr, mm, 'n', n)
[s, sep, m, info] = f08qy(job, howmny, select, t, vl, vr, mm, 'n', n)
```

3 Description

nag_lapack_ztrsna (f08qy) estimates condition numbers for specified eigenvalues and/or right eigenvectors of a complex upper triangular matrix T . These are the same as the condition numbers of the eigenvalues and right eigenvectors of an original matrix $A = ZTZ^H$ (with unitary Z), from which T may have been derived.

nag_lapack_ztrsna (f08qy) computes the reciprocal of the condition number of an eigenvalue λ_i as

$$s_i = \frac{|v^H u|}{\|u\|_E \|v\|_E},$$

where u and v are the right and left eigenvectors of T , respectively, corresponding to λ_i . This reciprocal condition number always lies between zero (i.e., ill-conditioned) and one (i.e., well-conditioned).

An approximate error estimate for a computed eigenvalue λ_i is then given by

$$\frac{\epsilon \|T\|}{s_i},$$

where ϵ is the *machine precision*.

To estimate the reciprocal of the condition number of the right eigenvector corresponding to λ_i , the function first calls nag_lapack_ztrexc (f08qt) to reorder the eigenvalues so that λ_i is in the leading position:

$$T = Q \begin{pmatrix} \lambda_i & c^H \\ 0 & T_{22} \end{pmatrix} Q^H.$$

The reciprocal condition number of the eigenvector is then estimated as sep_i , the smallest singular value of the matrix $(T_{22} - \lambda_i I)$. This number ranges from zero (i.e., ill-conditioned) to very large (i.e., well-conditioned).

An approximate error estimate for a computed right eigenvector u corresponding to λ_i is then given by

$$\frac{\epsilon \|T\|}{sep_i}.$$

4 References

Golub G H and Van Loan C F (1996) *Matrix Computations* (3rd Edition) Johns Hopkins University Press, Baltimore

5 Parameters

5.1 Compulsory Input Parameters

1: **job** – CHARACTER(1)

Indicates whether condition numbers are required for eigenvalues and/or eigenvectors.

job = 'E'

Condition numbers for eigenvalues only are computed.

job = 'V'

Condition numbers for eigenvectors only are computed.

job = 'B'

Condition numbers for both eigenvalues and eigenvectors are computed.

Constraint: **job** = 'E', 'V' or 'B'.

2: **howmny** – CHARACTER(1)

Indicates how many condition numbers are to be computed.

howmny = 'A'

Condition numbers for all eigenpairs are computed.

howmny = 'S'

Condition numbers for selected eigenpairs (as specified by **select**) are computed.

Constraint: **howmny** = 'A' or 'S'.

3: **select**(:) – LOGICAL array

The dimension of the array **select** must be at least $\max(1, \mathbf{n})$ if **howmny** = 'S', and at least 1 otherwise

Specifies the eigenpairs for which condition numbers are to be computed if **howmny** = 'S'. To select condition numbers for the eigenpair corresponding to the eigenvalue λ_j , **select**(*j*) must be set to *true*.

If **howmny** = 'A', **select** is not referenced.

4: **t**(*ldt*, :) – COMPLEX (KIND=nag_wp) array

The first dimension of the array **t** must be at least $\max(1, \mathbf{n})$.

The second dimension of the array **t** must be at least $\max(1, \mathbf{n})$.

The *n* by *n* upper triangular matrix *T*, as returned by nag_lapack_zhseqr (f08ps).

5: **vl**(*ldvl*, :) – COMPLEX (KIND=nag_wp) array

The first dimension, *ldvl*, of the array **vl** must satisfy

if **job** = 'E' or 'B', $ldvl \geq \max(1, \mathbf{n})$;

if **job** = 'V', $ldvl \geq 1$.

The second dimension of the array **vl** must be at least $\max(1, \mathbf{mm})$ if **job** = 'E' or 'B' and at least 1 if **job** = 'V'.

If **job** = 'E' or 'B', **vl** must contain the left eigenvectors of *T* (or of any matrix QTQ^H with *Q* unitary) corresponding to the eigenpairs specified by **howmny** and **select**. The eigenvectors **must** be stored in consecutive columns of **vl**, as returned by nag_lapack_zhsein (f08px) or nag_lapack_ztrevc (f08qx).

If **job** = 'V', **vl** is not referenced.

6: **vr**(*ldvr*, :) – COMPLEX (KIND=nag_wp) array

The first dimension, *ldvr*, of the array **vr** must satisfy

if **job** = 'E' or 'B', $ldvr \geq \max(1, \mathbf{n})$;
if **job** = 'V', $ldvr \geq 1$.

The second dimension of the array **vr** must be at least $\max(1, \mathbf{mm})$ if **job** = 'E' or 'B' and at least 1 if **job** = 'V'.

If **job** = 'E' or 'B', **vr** must contain the right eigenvectors of T (or of any matrix QTQ^H with Q unitary) corresponding to the eigenpairs specified by **howmny** and **select**. The eigenvectors **must** be stored in consecutive columns of **vr**, as returned by nag_lapack_zhsein (f08px) or nag_lapack_ztrevc (f08qx).

If **job** = 'V', **vr** is not referenced.

7: **mm** – INTEGER

The number of elements in the arrays **s** and **sep**, and the number of columns in the arrays **vl** and **vr** (if used). The precise number required, m , is n if **howmny** = 'A'; if **howmny** = 'S', m is the number of selected eigenpairs (see **select**), in which case $0 \leq m \leq n$.

Constraints:

if **howmny** = 'A', $\mathbf{mm} \geq \mathbf{n}$;
otherwise $\mathbf{mm} \geq m$.

5.2 Optional Input Parameters

1: **n** – INTEGER

Default: the first dimension of the array **t** and the second dimension of the array **t**. (An error is raised if these dimensions are not equal.)

n , the order of the matrix T .

Constraint: $\mathbf{n} \geq 0$.

5.3 Output Parameters

1: **s**(:) – REAL (KIND=nag_wp) array

The dimension of the array **s** will be $\max(1, \mathbf{mm})$ if **job** = 'E' or 'B' and 1 otherwise

The reciprocal condition numbers of the selected eigenvalues if **job** = 'E' or 'B', stored in consecutive elements of the array. Thus **s**(j), **sep**(j) and the j th columns of **vl** and **vr** all correspond to the same eigenpair (but not in general the j th eigenpair unless all eigenpairs have been selected).

If **job** = 'V', **s** is not referenced.

2: **sep**(:) – REAL (KIND=nag_wp) array

The dimension of the array **sep** will be $\max(1, \mathbf{mm})$ if **job** = 'V' or 'B' and 1 otherwise

The estimated reciprocal condition numbers of the selected right eigenvectors if **job** = 'V' or 'B', stored in consecutive elements of the array.

If **job** = 'E', **sep** is not referenced.

3: **m** – INTEGER

m , the number of selected eigenpairs. If **howmny** = 'A', **m** is set to n .

4: **info** – INTEGER

info = 0 unless the function detects an error (see Section 6).

6 Error Indicators and Warnings

info = $-i$

If **info** = $-i$, parameter i had an illegal value on entry. The parameters are numbered as follows:

1: **job**, 2: **howmny**, 3: **select**, 4: **n**, 5: **t**, 6: **ldt**, 7: **vl**, 8: **ldvl**, 9: **vr**, 10: **ldvr**, 11: **s**, 12: **sep**, 13: **mm**, 14: **m**, 15: **work**, 16: **ldwork**, 17: **rwork**, 18: **info**.

It is possible that **info** refers to a parameter that is omitted from the MATLAB interface. This usually indicates that an error in one of the other input parameters has caused an incorrect value to be inferred.

7 Accuracy

The computed values sep_i may over estimate the true value, but seldom by a factor of more than 3.

8 Further Comments

The real analogue of this function is nag_lapack_dtrsna (f08ql).

9 Example

This example computes approximate error estimates for all the eigenvalues and right eigenvectors of the matrix T , where

$$T = \begin{pmatrix} -6.0004 - 6.9999i & 0.3637 - 0.3656i & -0.1880 + 0.4787i & 0.8785 - 0.2539i \\ 0.0000 + 0.0000i & -5.0000 + 2.0060i & -0.0307 - 0.7217i & -0.2290 + 0.1313i \\ 0.0000 + 0.0000i & 0.0000 + 0.0000i & 7.9982 - 0.9964i & 0.9357 + 0.5359i \\ 0.0000 + 0.0000i & 0.0000 + 0.0000i & 0.0000 + 0.0000i & 3.0023 - 3.9998i \end{pmatrix}.$$

9.1 Program Text

```
function f08qy_example

fprintf('f08qy example results\n\n');

% Matrix in complex Schur form
n = nag_int(4);
T = [-6.0004 - 6.9999i, 0.3637 - 0.3656i, -0.1880 + 0.4787i, 0.8785 - 0.2539i;
      0 + 0i, -5.0000 + 2.0060i, -0.0307 - 0.7217i, -0.2290 + 0.1313i;
      0 + 0i, 0 + 0i, 7.9982 - 0.9964i, 0.9357 + 0.5359i;
      0 + 0i, 0 + 0i, 0 + 0i, 3.0023 - 3.9998i];

% Calculate the eigenvectors of T
select = [false];
vl = complex(zeros(n,n));
vr = complex(zeros(n,n));
job = 'Both';
howmny = 'All';

[T, vl, vr, m, info] = ...
f08qx( ...
    job, howmny, select, T, vl, vr, n);

[s, sep, m, info] = ...
f08qy( ...
    job, howmny, select, T, vl, vr, n);
disp('s:');
disp(s');
disp('sep:');
disp(sep');
tnorm = norm(T,1);
disp('Approximate error estimates for eigenvalues of T (machine-dependent)');
```

```
fprintf('%11.1e',x02aj*tnorm./s);
fprintf('\n\n%s %s\n', 'Approximate error estimates for right', ...
        'eigenvectors (machine-dependent)');
fprintf('%11.1e',x02aj*tnorm./sep);
fprintf('\n');
```

9.2 Program Results

f08qy example results

```
s:      0.9932      0.9964      0.9814      0.9779

sep:    8.4012     8.0215     5.8292     5.8292

Approximate error estimates for eigenvalues of T (machine-dependent)
  1.0e-15   1.0e-15   1.1e-15   1.1e-15

Approximate error estimates for right eigenvectors (machine-dependent)
  1.2e-16   1.3e-16   1.8e-16   1.8e-16
```
